


Combivis 6 – Installation & Registration

1 – Installation

1. After downloading the Combivis program, open the Setup_Combivis_studio_6.exe file
2. Select the language to use during installation from the drop-down menu and click “OK” to continue.



3. Additional components may be needed and can be installed automatically. Click “OK” to continue.




4. Once the program is ready to install, a Welcome screen will be displayed. Click "Next" to continue.



5. A license agreement will then be displayed. Select “I accept the agreement” then click “Next” to continue.




6. Select the destination location on the computer for the installation. The default folder is C:\Program Files\KEB\COMBIVIS_6. Click “Next” to continue.



7. Select the type of installation. This can be selected from the drop-down menu or the components can be manually selected/unselected. Select “Next” to continue.

Recommended is to select the “Compact Installation” (i.e. unselected Combivis Studio 6). Note: starting at v6.7, compact is the default; prior, studio was default.



Description: Compact vs. Studio (full) installation

The *Compact* installation of Combivis 6 generally fulfills the requirements for the majority of needs. This is a free version. Registration is optional and provides access to the *Documentation Database*; otherwise, there are no limitations to use.


Features include: access to parameters, startup wizards, upload/download parameter lists, digital oscilloscope, remote support, etc.

The full *Studio* installation includes additional components for control products (e.g. C6 embedded controllers, HMIs). This installation would generally only be needed when creating a structured logic or bootable program (e.g. Codesys, IEC61131 Development Environment).


This can be installed for free, with limited access. Here, after 1 hour the user will be prompted to save their project and shutdown the program (can be restarted again). Additionally, a *bootable* project file cannot be saved.

Access without restriction requires activation of a purchased license.


8. Select the Start Menu folder for the program's shortcuts. The default is KEB\COMBIVIS\COMBIVS studio 6. Select "Next" to continue.




9. Select which additional installations tasks should be performed.



10. The installation is now ready. To begin the installation, select “Install”.



11. The program will be installed.




12. When the process is complete, a computer restart will be needed to complete the installation. Select the option of when to do the restart, then click “Finish”.





2 – Combivis Registration (Compact Installation)


Once Combivis has been installed, the program can be opened. The upper left-hand corner will display “unregistered demo version”. Registration is optional, but provides access to the *Documentation Database*.



To register, select “Help” from the menu bar, then “Free customer registration”.



A prompt to enter the company name and registration key will appear.



The image shows a Windows-style dialog box titled "COMBIVIS 6 Registration". It has a blue title bar with standard window controls (minimize, maximize, close) on the right. The main area is white and contains two text input fields. The first field is labeled "Company name:" and has a placeholder text "Please enter your company name here...". The second field is labeled "Registration key:" and has a placeholder text "Please enter your registration key here...". Below these fields is a single "OK" button. At the bottom of the dialog, there is a note: "Note: To receive your registration information, please create a user account on the KEB Homepage and select 'COMBIVIS Registration' in your account data." followed by a link: "--> Visit KEB Homepage".

COMBIVIS 6 Registration

Company name:

Registration key:

OK

Note: To receive your registration information, please create a user account on the KEB Homepage and select 'COMBIVIS Registration' in your account data.
--> [Visit KEB Homepage](#)

To obtain the registration key, either select the “Visit KEB Homepage” link in the prompt or alternatively go to the webpage at:

<https://www.keb.co.uk/nc/my-account/combivis-registration>

At the website, the user must log-in (or create an account as needed) to receive the Company and Registration key information.

https://www.keb.co.uk/nc/my-account/combivis-registration

English | Company | Careers | News | Service | Web seminars | My Account | Contact

IoT | Control & Automation | Drive Technology | Motors & Gears | Brakes & Clutches | Automotive | e-mobility | Wind Power

Home » My Account » COMBIVIS Registration


Filter search Search ...

COMBIVIS Registration

How to register your COMBIVIS installation

To activate the registration of your COMBIVIS installation, please follow these steps:

1. In COMBIVIS, please click the menu command "Free customer registration", either in the quick start menu on the start page or in the main menu category "Help":




• Not registered, yet? Sign up here!

Your COMBIVIS registration key:

No registration key available! Your are not logged in. Login required!

2. In the following COMBIVIS dialog enter the data and confirm with "OK"



• Not registered, yet? Sign up here!

Your COMBIVIS registration key:

No registration key available! Your are not logged in.

2. In the following COMBIVIS dialog enter the data and confirm with "OK"

Once logged-in, the registration information will appear.

• Not registered, yet? Sign up here!

Your COMBIVIS registration key:

Company


Registration key

A screenshot of a web form showing registration information. It has two input fields: 'Company' and 'Registration key'. Both fields contain blacked-out text. A red arrow points to the right side of the 'Registration key' field.

This information can then be entered into the registration prompt in Combivis. Then, click “OK” to continue.

A screenshot of a Windows-style dialog box titled 'COMBIVIS 6 Registration'. It contains two text input fields: 'Company name:' with the placeholder text 'Please enter your company name here...' and 'Registration key:' with the placeholder text 'Please enter your registration key here...'. Below the fields is a single 'OK' button. At the bottom, there is a note: 'Note: To receive your registration information, please create a user account on the KEB Homepage and select 'COMBIVIS Registration' in your account data.' followed by a link: '--> Visit KEB Homepage'.



The user will then receive a prompt that the registration was successful. Click “OK” to continue.




Then, the user will be prompted to restart Combivis.



After Combivis has been restarted, the upper-left hand of the program will show the program registered to the company listed during registration.



Registration will also allow the user to access the *Documentation Database*. With this feature, right-clicking a parameter will bring up the option “*Find in documentation*”.




This will bring up the corresponding parameter manual and search the document for the selected parameter.




3 - Additional Information

3.1 – Check for Updates


After opening the Combivis, the program may prompt that updates are available.





The user may also check for updates by selecting “Help” from the menu bar, then “Check for updates”.



When selected, a menu will appear with available updates. Select “Start update” to continue.



The updates will be downloaded and when complete a prompt indicating “Update complete” will be displayed. Click “OK” to continue.



Afterwards, it may be necessary to restart the program and a prompt to restart will be given.




3.2 – Install additional Wizards


After installation of Combivis, additional Wizards not included in the installation package can be added.

In particular, this includes the wizard for the **T6 MCU Utility App**.

The wizard can be installed by checking for updates outlined in the previous section, unselecting “Show only recommended updates”, selecting “T6 Wizard” under the Programs section, then starting the update.





Once the installation process has been completed, shown below is the T6 MCU Utility App wizard (Node 0 T6 MCU).




3.3 – Install additional Wizards (alternative method)

As an alternative method, wizards can be manually added.

To manually install a wizard, open Combivis. From the “Tools” menu, select “Package Manager”.




The package manager window will appear and display the installed packages. To add a package, click “Install”.



This will open up a file explorer and after the file is located and selected, click “Open” to continue.


In the case of the T6 MCU Utility App wizard, the filename will be T6Wizard.package.




The user will then be prompted to select the installation type. “Typical setup” is recommended. Select “Next” to continue.




The user will then be prompted to select the program versions which the package installation should be applied to. Select the corresponding Combivis version and click “Next” to continue.



The installation will then start.



When the installation is complete, the user will be prompted to select Finish to exit the package installation wizard then restart the Combivis program. Click “Finish”, then select “Close” in the Package Manager window. Finally, close Combivis.



When Combivis is restarted, the user should be able to see a tab for the installed wizard when the corresponding device node is selected.

Shown below is the T6 MCU Utility App wizard.

